Camera

Functions

int	camera_open ()
int	camera_open_black ()
int	camera_open_at_res (enum Resolution res)
int	camera_open_device (int number, enum Resolution res)
int	<pre>camera_open_device_model_at_res (int number, enum Model model, enum Resolution res)</pre>
int	camera_load_config (const char *name)
void	set_camera_width (int width)
void	set_camera_height (int height)
int	get_camera_width (void)
int	get_camera_height (void)
int	camera_update (void)
pixel	get_camera_pixel (point2 p)
int	get_channel_count (void)
int	get_object_count (int channel)
const char *	get_object_data (int channel, int object)
int	get_object_data_length (int channel, int object)
double	get_object_confidence (int channel, int object)
int	get_object_area (int channel, int object)
rectangle	get_object_bbox (int channel, int object)
point2	get_object_centroid (int channel, int object)
point2	get_object_center (int channel, int object)
void	camera_close ()
void	set_camera_config_base_path (const char *const path)
const unsigned char *	get_camera_frame_row (unsigned row)
const unsigned char *	get_camera_frame ()

Detailed Description

Function Documentation

```
void camera_close ( )
```

Cleanup the current camera instance.

See also

```
camera_open_at_res
camera_open_device
```

int camera_load_config (const char * name)

Loads the config file specified by name. The system will look for the config in the base path.

Parameters

name The configuration to load. Configuration file names are case sensitive.

Note

Do NOT include the config file extension ".conf" in the name parameter.

Returns

1 on success, 0 on failure.

See also

```
set_camera_config_base_path
```

int camera_open ()

Opens the default system camera for use at LOW_RES (160x120).

Returns

1 on success, 0 on failure

See also

```
camera_open_at_res
camera_open_device
camera_close
```

int camera_open_at_res (enum Resolution res)

Opens the default system camera for use at a given resolution.

Parameters

res The resolution the camera should operate at. This can be:

- LOW_RES (160x120)
- MED_RES (320x240)
- HIGH_RES (640x480)

Warning

Only LOW RES is currently supported. The function will fail for other resolutions.

Returns

1 on success, 0 on failure

See also

```
camera_open_device
camera_close
```

int camera_open_black ()

Opens the default system camera for use at LOW_RES (160x120). This will improve frame rates for the black Logitech camera

Returns

1 on success, 0 on failure

See also

```
camera_open_at_res
camera_open_device
camera_close
```

```
int camera_open_device ( int number,
enum Resolution res
)
```

Opens a camera for use.

Parameters

number The camera's id. 0 is the first camera, 1 is the second camera, etc.

res The resolution the camera should operate at. This can be:

- LOW_RES (160x120)
- MED_RES (320x240)
- HIGH_RES (640x480)

Warning

Only LOW RES is currently supported. The function will fail for other resolutions.

Returns

1 on success, 0 on failure

See also

camera_open

camera_close

Opens a camera for use.

Parameters

number The camera's id. 0 is the first camera, 1 is the second camera, etc.

res The resolution the camera should operate at. This can be:

- LOW RES (160x120)
- MED_RES (320x240)
- HIGH RES (640x480)

model The camera model

- WHITE_2016 The white 2016 Botball camera
- BLACK_2017 The black 2017 Botball camera

Warning

MED RES is supported only for the BLACK 2017 camera and HIGH RES is not supported

Returns

1 on success, 0 on failure

See also

```
camera_open
```

camera_close

int camera_update (void)

Pulls a new image from the camera for processing.

Returns

1 on success, 0 on failure.

const unsigned char* get_camera_frame ()

Retrieves the current camera frame as a BGR (BGR888) array. The returned pointer is invalid after **camera_update()** is called again.

Returns

the current BGR888 camera frame.

const unsigned char* get_camera_frame_row (unsigned row)

Retrieves the current camera frame row as a BGR (BGR888) array. The returned pointer is invalid after camera_update() is called again.

Returns

the current BGR888 camera frame row.

int get_camera_height (void)

Gets the camera's y resolution.

Attention

This value might be different than the previously set y resolution. Never assume the y resolution.

Returns

The camera's y resolution, in pixels.

pixel get_camera_pixel (point2 p)

Gets the color of a pixel.

Parameters

p The point at which the pixel lies.

Returns

The rgb value of the pixel located at point p.

Note

A (r, g, b) value of (-1, -1, -1) will be returned for points that are out of range.

```
int get_camera_width ( void )
```

Gets the camera's x resolution.

Attention

This value might be different than the previously set x resolution. Never assume the x resolution.

Returns

The camera's x resolution, in pixels.

```
int get_channel_count ( void )
```

Returns

Number of channels in the current configuration.

See also

get_object_count

Returns

The object's bounding box area. -1 is returned if the channel or object doesn't exist.

```
rectangle get_object_bbox ( int channel, int object )
```

Returns

The bounding box of the given object on the given channel.

```
point2 get_object_center ( int channel, int object )
```

Returns

The (x, y) center of the given object on the given channel.

```
point2 get_object_centroid ( int channel, int object )
```

Returns

The (x, y) centroid of the given object on the given channel.

```
double get_object_confidence ( int channel, int object )
```

Returns

The confidence, between 0.0 and 1.0, that given object on the given channel is significant. If the channel or object doesn't exist, 0.0 is returned.

int get_object_count (int channel)

Parameters

channel The channel to scan for objects.

Note

Objects are sorted by area, largest first.

Returns

Number of objects in the given channel, -1 if channel doesn't exist.

See also

get_channel_count

```
const char* get_object_data ( int channel, int object )
```

Returns

The string data associated with a given object on a given channel. If there is no data associated, 0 is returned.

Note

This data is not guaranteed to be null terminated.

This string pointer will be invalid after a call to camera_update()

See also

```
get_object_data_length
```

Returns

The length of the string data associated with a given object on a given channel. If there is no data associated, 0 is returned. If the channel or object is invalid, 0 is returned.

See also

get_object_data

```
void set_camera_config_base_path ( const char *const  path )
```

Sets the path in which to look for camera configurations.

Parameters

path the absolute directory path in which to look for camera configurations.

void set_camera_height (int height)

Sets the camera's y resolution.

Warning

Setting the camera height is not currently supported.

Parameters

width The height in pixels

void set_camera_width (int width)

Sets the camera's x resolution.

Warning

Setting the camera width is not currently supported.

Parameters

width The width in pixels